

6. Modifying a business object (BO)

🌐 Language: [Deutsch](#) · [English](#)

🔧 6. Modifying a business object (BO)

Modify a BO via REST – PUT on self, subforms via subBos insert/update/delete.

HOW-TO

DEVELOPER

UPDATED: JUL 2026

APPLIES TO NUCLOS 4.2026.X

On this page

- [Subforms](#)
- [Related pages](#)

A record read earlier can be modified via **PUT** on the self link – attributes are edited as when creating (data types see [meta information](#)).

Subforms

For performance reasons, subforms are not read with the BO but via their own links. Changes are passed in the object JSON under subBos with insert/update/delete per reference attribute:

Fehler beim Rendern des Makros 'code': Ungültiger Wert für den Parameter 'com.atlassian.confluence.ext.code.render.InvalidValueException'

```
"subBos": {
  "insert": {
    "{refAttrId}": [
      { "boId": null, "boMetaId": "{boMetaId}", "attributes": { ... } }
    ]
  },
  "update": {
    "{refAttrId}": [
      { "boId": 123, "boMetaId": "{boMetaId}", "attributes": { ... } }
    ]
  },
  "delete": { "{refAttrId}": [ 456 ] }
}
```

- **insert:** new rows like a normal BO (via a blank).
- **update:** append only the changed rows – unchanged ones need not be sent.
- **delete:** only the ids of the rows to delete.

Related pages

⚙️ 7. Deleting a business object (BO)

Delete.

[Open](#)

⚙️ 5. Creating a business object (BO)

Create.

[Open](#)