

Object import

 Language: [Deutsch](#) · [English](#)

Object import

Import CSV files – standard vs. direct import, multiple structure definitions and ordering.

HOW-TO

APPLICATION DEVELOPER

UPDATED: JUL 2026

APPLIES TO NUCLOS 4.2026.X

On this page

- [What is the object import?](#)
- [File & import mode](#)
- [Assign structure definitions](#)
- [Related pages](#)

What is the object import?

In the **Object import** mask you assign one or more [structure definitions](#) to a source file and start the import. *Menu: Import & Export Object import.*

File & import mode

Under **File** the **CSV** file is uploaded to a server directory.

Mode	Behaviour
Standard import	creates data via Nuclos storage mechanisms – rules are executed.
Direct import	writes straight into the DB (no rules) – much faster for large volumes; extra attributes nuclosProcess and nuclosState.



Direct import

On direct import, **state and action are imported by name only** (depending on the current context language). **Run in transaction** reads block-wise (performance); the result is written to the **log file**.

Objektimport - Ergebnis

Objektimport | nudos_import

Liste

Details

Extras

Importieren

Import abbrechen

Einstellungen

Beschreibung

Import des Kunden

Importmodus

Standardimport

Datei

KundeZumImport.csv

Transaktion

Status

Fortschritt

Import läuft nicht

Status

Ergebnis

Strukturdefinitionen

CSV Strukturdefinition

Reihenfolge

Object import mask.

Assign structure definitions

On the **Structure definition** tab, assign one or more definitions. The **order** determines the import sequence – important for dependencies.

Objektimport - Ergebnis

Objektimport | nuclos_import

Strukturdefinition | Import Ki

Liste

Details

Extras

Importieren

Import abbrechen

Einstellungen

Beschreibung

Import des Kunden

Importmodus

Standardimport

Datei

KundeZumImport.csv

Transaktion

Status

Fortschritt

Import läuft nicht

Status

Ergebnis

Strukturdefinitionen

CSV Strukturdefinition

Reihenfolge

Import Kunde

1

Assigning structure definitions.

Running an import

How-to (existing structure definition): open the target entity *Actions* *Import* upload the file and choose the structure definition check import mode/preview *Start* check the import log.

Related pages

Structure definition

Mapping.

[Open](#)

Import and export

Overview.

[Open](#)

