

4.7 SEPA: Nuclet parameters

Language: Deutsch · English

4.7 SEPA: Nuclet parameters

Configure the SEPA Nuclet parameters (message ID schemes, export directory, prefixes, defaults) under Nuclet Management.

REFERENCE

INTEGRATORS

UPDATED: JUL 2026

APPLIES TO NUCLOS 4.2026.X

On this page

- [Related pages](#)



Machine-translated – under review

This page was machine-translated from German as a first draft and is currently under review. The authoritative source remains the **German original** (see the language switch above).

4.7.1 Configuration of the Nuclet parameters

The Nuclet parameters used are set up via "Configuration > Nuclet Management > Parameters".

Parameter	Short description	Examples
SEPA Message Id Scheme	Scheme for generating SEPA message IDs. The message IDs are used to identify SEPA messages uniquely.	"ABCD-MID-{000000}", where - ABCD is an abbreviation for your company and 000000 indicates the length of the IDs to be generated
SEPA Payment Information Id Scheme	Scheme for generating SEPA payment information IDs. The payment information IDs are used to identify SEPA payment instructions uniquely.	"ABCD-PIID-{messageId}-{0000}", where - ABCD is an abbreviation for your company and 000000 indicates the length of the IDs to be generated
SEPA Batch Booking ¹	Yes/No information for marking SEPA batch bookings	"true" or "false"
SEPA Credit Transfer Export	activation of the SEPA credit-transfer export	"active" / "inactive"
SEPA Credit Transfer Export Prefix ¹	prefix for SEPA credit-transfer exports	"CreditTransfers"
SEPA Credit Transfer Filename Prefix ¹	prefix for the filenames of the SEPA credit-transfer exports	"sepa_sct"
SEPA Direct Debit Export	activation of the SEPA direct-debit export	"active" / "inactive"
SEPA Direct Debit Export Prefix ¹	prefix for SEPA direct-debit exports	"DirectDebits"
SEPA Direct Debit Filename Prefix ¹	prefix for the filenames of the SEPA direct-debit exports	"sepa_sdd"
SEPA Direct Debit Payment Type ¹	default value for the SEPA payment type	"BASIC" for basic direct debits, or "B-2-B" for business direct debits
SEPA Export Directory ¹	file directory for storing the SEPA export files	- on Windows: "D:\nuclos\Data\SEPA" - on Linux: "/home/nuclos/Data/SEPA"

SEPA Initiator ¹	default initiator for SEPA exports	<i>your company name</i>
SEPA Time Zone ¹	default value for the time zone to be used in SEPA exports	"Europe/Berlin"

Table 4.7.1: Nuclet parameters

 **Note on ¹:**

The parameters marked with this footnote serve as default values for automatically generated SEPA exports. These are all SEPA exports created via a job from the job control.

For manually created SEPA exports these parameters are not relevant.

Related pages

 **Nuclet: SEPA**

SEPA Nuclet data sheet

[Open](#)

 **Interfaces**

All integrations

[Open](#)