

4.7 DATEV: Nuclet parameters

Language: [Deutsch](#) · [English](#)

4.7 DATEV: Nuclet parameters

Nuclet parameters – part of the DATEV Nuclet documentation (export of CSV files for further processing in DATEV (accounting)).

REFERENCE

INTEGRATORS

UPDATED: JUL 2026

APPLIES TO NUCLOS 4.2026.X

On this page

- [Related pages](#)



Machine-translated – under review

This page was machine-translated from German as a first draft and is currently under review. The authoritative source remains the **German original** (see the language switch above).

4.7.1 Configuration of the Nuclet parameters

The Nuclet parameters used are set up via "Configuration > Nuclet Management > Parameters".



All parameters to be configured serve as default values for the job control – i.e. this integration step is only necessary if the DATEV exports are to be run automatically.

The parameters themselves must not be deleted, however, so that the server rules remain functional.

Parameter	Short description	Examples
DATEV File Directory	file directory for the output of DATEV export files (see section 4.6)	- on Windows: "D:\nuclos\Data\DATEV" - on Linux: "/home/nuclos/Data/DATEV"
DATEV File Encoding	character set of the DATEV export files	UTF-8, ISO-8859-1, ISO-8859-15, US_ASCII, UTF-16BE, UTF-16, UTF-16LE, etc.
DATEV Field Separator	field separator for the DATEV CSV	; (semicolon) , (comma)
DATEV Text Separator	text separator for the DATEV CSV	" (double quote) ' (apostrophe)
DATEV Header Row	flag for including a header row in the DATEV export	- true (export with header row) - false (export without header row)
DATEV Client Billing Export Prefix	name prefix for invoice exports	DATEV invoices
DATEV Client Export Prefix	name prefix for customer exports	DATEV customers
DATEV Turnover Export Prefix	name prefix for turnover exports	DATEV turnover

Table 4.7.1: Nuclet parameters

Related pages

 **Nuclet: DATEV
(available in the trade
Nuclet)**

DATEV Nuclet data sheet

[Open](#)

 Interfaces

All integrations

[Open](#)