

List views

 Language: [Deutsch](#) · [English](#)

List views

Configure columns, save views and share them with user groups – shared across Web and Desktop client.

REFERENZ	USER	UPDATED: JUL 2026	APPLIES TO NUCLOS 4.2026.X
----------	------	-------------------	----------------------------

On this page

- [Configure](#)
- [Share settings](#)
- [Nuclet assignment & layout restriction](#)
- [Permission](#)
- [Additional setting](#)
- [Related pages](#)



Shared source

From Nuclos 4.18 the Web and Desktop client share the same table settings – maintain views in either client and use them mutually.

List views apply to result lists *and* subforms. Show/hide columns, change sorting and widths. Configured views can be published to user groups.

Configure

Einstellungen der Sidebar

Order

Ansicht

Spalten Titel / Info

Spalten

Nuclos-Test Name ändern

Verfügbare Spalten

Verfügbare Spalten	Ausgewählte Spalten
Customer address	Order number
Order date	Customer
Delivery date (priority)	
Discount	
Note	
Approved credit limit	
Confirmation	
Order	
Send date	
Besitzer	
Status	
Statusnumeral	
Statusname	
Aktion	

Column settings in the Web Client.

In the Web Client the gear sits in the toolbar; in the Rich Client with a vertical toolbar use a column header's context menu.

Share settings

Only via the Web Client (right **Share settings**): user menu **Manage settings**. Select a view and assign it to a user group (share).

Einstellungen

G...	Typ	Businessob...	Layout	Name
...	...	order	...	...
🌐	📄	MyOrdersAndCusto...	Customer	Default
🌐	📄	Order		Nuclos-Test
🌐	📄	Order		Default
🌐	📄	OrderPosition	Example priority ord...	Default
🌐	📄	OrderPosition	Example priority ord...	Default
🌐	📄	OrderPosition	Customer	Default
🌐	📄	OrderPosition	Example order	Default

Zugewiesene Benutzergruppen

☐ Example user

Einstellungen

Manage settings.

Shared settings show a globe icon. After changes, **share again** and **discard change** are available (Desktop client: „reset current list view to template“).

Nuclelet assignment & layout restriction

When sharing, a setting can be assigned to the business object's Nuclelet. Subform settings are bound to the layout by default; **remove layout restriction** makes them apply across layouts.

Permission

 **Right**
The right **Adjust table settings** is required to persist views. Without it, sorting/widths are temporary only.

Additional setting

Key	Description
sideviewMenuWidth	width of the result-list sidebar (Web Client only): -1 = collapsed, 1 = full window, otherwise width in px

Related pages

 **Search filters**
Filters per business object.
[Open](#)

 **Colored rows**
Color rows.
[Open](#)