

Standalone client

 Language: [Deutsch](#) · [English](#)

Standalone client

The standalone client starts the Rich Client without Web Start – as a copyable directory with a start script.

HOW-TO

USER

UPDATED: JUL 2026

APPLIES TO NUCLOS 4.2026.X

On this page

- [Configuration in the installer](#)
- [Start & distribution](#)
- [Related pages](#)

Since Nuclos 4.8 you can install a **standalone client** that runs Nuclos without Web Start.

Configuration in the installer

The "client configuration" step has two optional parameters:

- **Server host** – if left empty, localhost is used (client then only usable on the server).
- **Java runtime** – if given, it is bundled; otherwise a system runtime is used. Without a system runtime this is required.

The screenshot shows the 'Client configuration' window of the Nuclos 4.22.0 installer. The window has a title bar with the text 'Nuclos 4.22.0 Installation' and standard window controls. Below the title bar, there is a header section with the text 'Client configuration' and 'Configure client settings'. To the right of this header is the Nuclos logo, which consists of a stylized blue and grey icon followed by the text 'NUCLOS' and 'OPEN SOURCE ERP' below it. The main area of the window contains four checked checkboxes: 'Start client as single instance (webstart only)', 'Install desktop client', and 'Enable launcher'. There is also an unchecked checkbox for 'Install web client'. Below these checkboxes are two text input fields. The first is labeled 'Server host (optional for stand-alone client)' and contains the text 'smuc4292.muc'. The second is labeled 'Java Runtime (optional for stand-alone client)' and contains the text 'E:\Konfigurationsplanung\jre\1.8.0_92'. To the right of the second input field is a 'Browse' button. At the bottom of the window, there are three buttons: 'Previous', 'Next', and 'Cancel'. The 'Next' button is highlighted with a dashed border.

Nuclos 4.22.0 Installation

Client configuration
Configure client settings

☒ Start client as single instance (webstart only)
☒ Install desktop client
☒ Enable launcher
☐ Install web client

Server host (optional for stand-alone client)

Java Runtime (optional for stand-alone client)

◀ Previous Next ▶ Cancel

Client configuration in the installer (server host, Java runtime).

Start & distribution

Under `client` in the install directory you'll find everything including start scripts: `nuclos.cmd` (Windows) / `nuclos.sh` (Unix). On first start the all-in-one `nuclos.jar` is unpacked and the client starts. The whole directory can be copied to other machines.

Libraries

SMUC4292

System (C:)

Admin (D:)

Data_E (E:)

_old

DESoftware

Konfigurationsplanung

NetBackup Temp

Nuclos

bin

client

conf

data

extensions

extra

logs

Name ^	Date modified	Type	Size
extensions	24.11.2017 10:39	File folder	
jre	24.11.2017 10:39	File folder	
lib	24.11.2017 10:39	File folder	
all-in-one-85f4b97d87e915dcd12f16346987...	24.11.2017 10:39	gz Archive	25.020 KB
client.properties	24.11.2017 10:39	PROPERTIES File	1 KB
nuclos.cmd	24.11.2017 10:39	Windows Command ...	3 KB
nuclos.sh	24.11.2017 10:39	SH File	1 KB

The client directory with start scripts.



Older versions

Before Nuclos 4.8 the `client` directory was created but the start scripts were missing – you can take these from a 4.8+ version.

Related pages



Launcher (DE)

Start the Rich Client via the Launcher.

[Open](#)



Installation (DE)

Install Nuclos.

[Open](#)